

Continue



Android TV Box Hard Reset



How do i reset my smart tv android. How to perform a forced factory reset on an android tv. How to reset an android tv box. How to reboot an android tv. How to reset an android smart tv.

Item ID: 00159487 / Last Modified: 06/28/2022 There are three different ways to reset Android TV™ or Google TV™ depending on the issue you are experiencing: Step 1 (power reset/reboot) is always recommended first, this solves many problems and does not affect the stored information. Step 2 (Factory Reset) is the next step that will remove all custom settings when resetting the TV to factory specifications. Step 3 (forced factory reset) is the last option and will also remove all custom settings when resetting the TV to factory settings. Use this option if you cannot access the TV through the menu, remote control, or otherwise. Before you start IMPORTANT! This article only applies to Android TV or Google TV models. If you are not sure, you can check the TV type. Make sure the TV is turned on and disconnect any external USB devices from the TV. Note: You can watch a video with these options or go to more detailed steps. Power Recovery/Reboot and Factory Data Reset Steps Check after each step to see if the problem is resolved. Step 1: Power reset or reboot options. If a power cord is available, try a power reset. If not, use one of the reboot options. Unplug the TV's power cord from the wall outlet, wait two minutes, and then plug the power cord back in. Restart the TV using the supplied remote control: press and hold the POWER button until "Off" appears on the screen. Press and hold the POWER button until the à menu appears, select Restart Restart from the menu. On the remote control: Press (Quick Settings) → Settings → System → Restart → Restart Press HOME → go to Settings → About → Restart → Restart Press HOME → go to Settings → Device Settings → About → Restart → Restart After restarting using the remote control or the menu, the TV will automatically turn off and turn on again after a short time. Step 2: Factory Reset WARNING! A factory reset will delete all custom settings on the TV,Google™ account, apps, channel, camera information, parental controls and Wi-Fi settings. You can sync your apps with your Google account and restore some app data after factory reset. Depending on the TV menu, follow the steps below. Press HOME → go to Settings → Device settings or Accounts and sign in → Google → Select synced apps → select items to sync → Sync now Press HOME → go to Settings → Google → Select under Sync select synced apps → select items to sync → Sync now Press HOME à go to Settings à Personal à Google à Select synced apps in Sync à select items to sync off à select items to sync à Sync now Factory reset after firmware update for 750H models. When the HOME screen appears on the TV screen On the supplied remote control, press the (Quick Settings) button or the HOME button depending on the TV, select settings. The next steps vary depending on the TV menu options: Select System - About - Reset - Factory data reset - Erase everything - Yes. Select Device settings → Reset → Factory data reset - Erase everything - Yes. Select "Storage and recovery" ■ "Factory data reset" ■ "Erase everything" ■ "Yes". If the HOME screen does not appear (HOME button on the remote control does not work) If the remote control has an ACTION MENU or (Quick Settings) button and the response is displayed, follow the steps below. Press the ACTION MENU or (Quick Settings) button. Select Settings → Device Settings. The next steps depend on your TV's menu options: select System → About → Reset → Factory data reset → Erase all → Yes. Quick Setup) and NO response, follow the steps below. tv remote control, Press HELP or press (Enter) and then select Help. Select Manual (Help). Select settings Factory data reset Erase all Yes For other models (using the Help button) Press the HELP button on the supplied remote control Select TV or TV Select settings The next steps depend on the TV menu options: Select Device settings → Reset → Factory data reset → Erase all ■ Yes Select Save and Restore ■ Factory data reset ■ Erase everything ■ Yes Notes: Factory data reset may take some time. Wait for the process to complete. After selecting clear all, you may need to enter a PIN (if set on the TV). After the factory reset process is complete, the TV will start the initial setup wizard. You must agree to Google's Terms of Service and Google's Privacy Policy. If you're having issues with your Amazon Fire TV Stick remote, it's worth resetting the remote to potentially resolve these issues. The reset process varies by model, and we'll show you the processes for the most popular Fire TV Stick remotes. RELATED: How to Fix a Broken Amazon Fire TV Stick Remote Resetting a Basic Fire TV Stick Remote If you have a basic remote that looks like the one below, follow these steps to reset it. Press and hold the Home button, then press the Menu button (three horizontal lines) three times. Release the Home button, then press the Menu button nine times. Remove the batteries from the remote control. Unplug the Fire TV Stick and wait a while. Put the batteries back in the remote and turn on the Fire TV Stick. When the Fire TV Stick home screen opens, press and hold the Home button on the remote for 40 seconds. The setup will be completed in a minute. Restore default settings The first generation Fire TV Stick remote control The first generation Fire TV Stick remote control does not have power and volume buttons, but you can still reset it by following these steps. Unplug your Fire TV Stick and wait a minute. On the remote control, press and hold the left button and the menu button at the same time for 12 seconds. Release the buttons and wait five seconds. Remove the batteries from the remote control. Connect the Fire TV Stick's power cord to turn on the device, then wait a minute. Insert the batteries back into the remote control. Press the Home button on the remote control. RELATED: How to Update Your Amazon Fire TV Stick 2nd and 3rd Generation, Voice Remote Lite, Smart TV Remote, and Soundbar Remote If Your Fire TV Stick Doesn't Look Like It Used to, You Have a 2nd or 3rd generation, Voice Remote Lite, Smart TV Remote or Soundbar. In this case, you will reset the remote as follows. The location of the remote control may vary slightly, but you will use the same keys. Unplug your Fire TV Stick and wait 60 seconds. On the remote control, press and hold the Left, Menu, and Back buttons at the same time for 12 seconds. Release the buttons and wait five seconds. Remove the batteries from the remote control. Connect the Fire TV Stick's power cord and turn on the device. Then wait 60 seconds. Insert the batteries back into the remote control. Press the Home button on the remote control. And it's all. Your remote has been reset and re-paired to your Fire TV Stick. Enjoy! If you're still having issues with your device, consider updating or resetting your Fire TV. Both can solve many problems on your streaming device. RELATED: How to Reset Your Amazon Fire TV How-To Geek is where you want the experts to explain the technology. Since launching in 2006, our articles have been read over a billion times. Do you want to know more? Before you can start using your Fire TV Stick, you need to pair your remote. Process may vary depends on your model and not every remote is compatible with every generation of Amazon Fire TV. Here's how to pair or reset your Fire TV Stick remote. Learn more: How to add, update, and remove apps on your Fire TV Stick Fortunately, the pairing process with the Fire TV Stick is relatively quick, so you can set up and watch content. First, make sure the TV is on and the remote control is within 3m of the TV. Then just press and hold the Home button on the remote control for ten seconds. You should see a flashing light on the top of the remote, then the screen will confirm that the remote is paired. If you don't see any of these, try removing or replacing the remote control batteries and wait thirty seconds before trying again. If it still doesn't work, see the next section to learn how to reset your Fire TV Stick remote. First, unplug your Fire TV and wait a full minute. Then press and hold the Left, Menu and Back buttons at the same time. We understand that you may need to do several things at once, but you can hold down the first two buttons with your thumb because the back button is just below the left button. Here's a diagram of the corresponding button for your reference: Adam Birney / Android Power Hold all three buttons for twelve seconds, then release them and wait five seconds. Then remove the batteries from the remote, reconnect the Fire TV, and wait another minute. Finally, put the batteries back into the remote control and press the start button. The LED on the remote will flash blue to indicate successful pairing. Note that you won't see the flashing lights if you're using an Alexa Voice Lite remote (one that doesn't have power or volume up/down buttons). Resetting the first generation Alexa Voice Remote is the same as before, except you have to hold down fewer buttons. Unplug your Fire TV and wait a minute. Press and hold the left button and the menu button at the same time. Hold them for twelve seconds. Edition and wait five seconds. Remove the batteries from the remote control. Plug the Fire TV back in and wait a while. Put the batteries back into the remote control. Press the home button on the remote control. The procedure for Fire TV Basic Edition is different, so follow it carefully. Press and hold the home button. Press the menu button three times at the same time. Release the Home button and press the Menu button nine times. Remove the batteries from the remote, unplug the Fire TV and wait a while. When the time is up, put the batteries back in the remote and plug the Fire TV back in. When the home screen appears, press and hold the home button for 40 seconds. The setup process should then take a minute. Read more: How to remove a device from Alexa FAQ Are Fire TV Stick remotes universal? Yes, many Fire TV remotes are interchangeable, but not all. When replacing a lost or damaged remote, make sure it's compatible with your Fire Stick model and generation. Can you replace the Fire TV Stick remote? Yes, you can exchange your Fire TV remote for a new one. However, make sure the replacement is compatible with your Fire Stick model and generation before purchasing. Can I use my phone as a Fire TV Stick remote? Yes, there is a mobile app for Android and iPhone that you can use to control the Fire TV Stick from your smartphone. How to pair other Fire TV remotes? First, go to Settings on your Fire TV. Then select Bluetooth drivers and devices. Select Amazon Fire TV remotes and press and hold the home button for 10 seconds to pair the remote. Amazon Fire TV Streaming TV Streaming TV

